

Chaos Vantage Command Line Options

This page provides information about the command line parameters available for Chaos Vantage.

Overview

Chaos Vantage can be run from Windows' Command Prompt with the listed below command-line arguments.

Please note that the **vantage_console.exe** has to be used instead of the **vantage.exe** located in *C:\Program Files\Chaos Group\Vantage* in order for the command-line arguments to work.

General

-help (-h) – Prints all available arguments.

-version (-v) – Prints current installed version, build number, build hash, build date of Chaos Vantage.

-quiet (-q) – Doesn't print rendering progress.

-debugLogFile (-dLog) – Outputs the debug log to a specified file. If the file could not be accessed or created, the default one (in %AppData% or %TEMP%) will be used.

-linkPort=<integer> (-lp) – Sets Live Link port.

-sceneFile=<filename> (-s) – Loads specified scene file.

-configFile=<filename> (-conf) – Loads specified .vantage file.

-camera=<name> (-cam) – Sets render camera.

-sceneStateName=<name> (-ssName) – Applies the specified scene state.

Devices(GPUs)

-deviceList (-dl) – Prints a list of devices available for rendering.

-device=<integer> (-d) - Uses the device at given index in the list. Can be passed multiple times.