

Sharing vrlclient.xml over a network

This page gives details on how to use the .vrlclient.xml file from a central location on your network.

Overview

An instance of the Chaos License Server that uses the same user account may be installed more than once on the same internal network when on different workstations or servers to act as a redundancy measure. You can also use V-Ray [environment variable](#) VRAY_AUTH_CLIENT_FILE_PATH.

In this case, the vrlclient.xml file could be stored on a centrally accessible location. The variable should look like:

VRAY_AUTH_CLIENT_FILE_PATH=//SERVER/path/to/directory/

The environment variable should point to the directory where the **vrlclient.xml** file resides.

vrlclient_example.xml

```
<VRLClient>
  <LicServer>
    <Host>IP address or FQDN of the primary license server</Host>
    <Port>30304</Port>
    <Host1>IP address or FQDN of the secondary license server if exists</Host1>
    <Port1>30304</Port1>
    <Host2>IP address or FQDN of the third license server if exists</Host2>
    <Port2>30304</Port2>
    <User></User>
    <Pass></Pass>
  </LicServer>
</VRLClient>
```

Windows


By default the *vrlclient.xml* location is **C:\Program Files\Common Files\ChaosGroup**

Setting the path and variables in Windows 8 and Windows 10

1. On the desktop or through Windows Explorer, **right-click** on the **This PC** icon and choose **Properties** from the menu.
2. Click the **Advanced System Settings** link in the left column.
3. In the System Properties window, click on the **Advanced** tab, then click the **Environment Variables** button near the bottom of that tab.
4. In the Environment Variables window (pictured below), highlight the **Path** variable in the "System variables" section and click the **Edit** button. Add or modify the path lines with the paths you want the computer to access. Each different directory is separated with a semicolon as shown below.

Setting the path and variables in Windows 7

1. From the Desktop, right-click the **Computer** icon and select **Properties**. If you don't have a Computer icon on your desktop, click the Start button, right-click the **Computer** option in the Start Menu, and select **Properties**.
2. Click the **Advanced System Settings** link in the left column.
3. In the System Properties window, click on the **Advanced** tab, then click the Environment Variables button near the bottom of that tab.
4. In the Environment Variables window (pictured below), click on **New..** in the "System variables" section.
5. Add the **Variable name** - VRAY_AUTH_CLIENT_FILE_PATH
6. Add the **Variable value** - //SERVER/path/to/directory/



macOS

By default the `vrclient.xml` location is `/Users/YourUsername/.ChaosGroup` folder.

In order for the variable to be valid for both terminal and GUI, you need to set it using either **enviroment.plist** or **launchctl** depending on your macOS version.

If you are running **OS X Yosemite or newer**, you should add the variable using an `environment.plist` file.

- Download the attached `setenv.chaos_group.VRAY_AUTH_CLIENT_FILE_PATH.plist` example file and edit the location of **vrclient.xml** file using a text editor.

- Place the edited file in `/Library/LaunchAgents/` directory.

[Download Example File](#)

If you are running **OS X Mavericks or older** you should add the variable in the **launchd.conf** file.

Open the file using super-user privileges: `sudo vi /etc/launchd.conf`

Next, add the variable as follows: `setenv VRAY_AUTH_CLIENT_FILE_PATH //SERVER/path/to/directory`

Then save the file.

Note that you need to reboot the machine after that in order for the changes to take effect.

You can check the web for more details on setting environment variables for your Mac version.

Linux

By default the **vrclient.xml** location is ***/home/YourUsername/ChaosGroup*** folder.

Set the **VRAY_AUTH_CLIENT_FILE_PATH** environment variable to point to the **vrclient.xml** file.

For **bash/ksh**: `export VRAY_AUTH_CLIENT_FILE_PATH=//SERVER/path/to/directory/`

For **csh/tcsh**: `setenv VRAY_AUTH_CLIENT_FILE_PATH=//SERVER/path/to/directory/`

To set the variable system wide create a custom.sh shell script in ***/etc/profile.d/***